


Remarks:

If online debug by ICD2 is required, please use the following `_CONFIG1` to use PGx2 pins



The screenshot shows the MPLAB IDE v8.30 interface. The main window displays the source code for `D:\mcc30\projects\PIC24_Eval_RevC\PIC24FJ256GA110\QC Demo TY240\MainDemo.c`. The code includes a configuration line that is highlighted with a red box:

```
#include "MainDemo.h"
|
// Configuration bits
// Configure fast RC oscillator with PLL and RC15 pin for Fosc/2 function
CONFIG2(FMOSC_FRCPLL & OSCIOFNC OFF)
_CONFIG1(JTAGEN_OFF & FWDTEN_OFF & ICS_PGx2) // JTAG off, watchdog timer off
//_CONFIG1(JTAGEN_OFF & FWDTEN_OFF)
```